

Guide cablabel S3



Configuration of cab printers
for use with cablabel S3

Family
cab devices
Labelling Software cablabel S3

Edition : 04/2015

Copyright

This documentation as well as translation hereof are property of cab Produkttechnik GmbH & Co. KG.

The replication, conversion, duplication or divulgement of the whole manual or parts of it for other intentions than its original intended purpose demand the previous written authorization by cab.

Editor

Regarding questions or comments please contact cab Produkttechnik GmbH & Co. KG.

Topicality

Due to the constant further development of our products discrepancies between documentation and product can occur.

Please check www.cab.de for the latest update.

Germany

cab Produkttechnik
GmbH & Co KG

Postfach 1904
D-76007 Karlsruhe
Wilhelm-Schickard-Str. 14
D-76131 Karlsruhe

Telefon +49 721 6626-0
Telefax +49 721 6626-249
www.cab.de
info@cab.de

France

cab technologies s.a.r.l.
F-67350 Niedermodern
Téléphone +33 388 722 501
www.cab-technologies.fr
info@cab-technologies.fr

USA

cab Technology Inc.
Tyngsboro MA, 01879
Phone +1 978 649 0293
www.cab.de/us
info.us@cab.de

Taiwan 亚洲

cab Technology Co., Ltd.
希愛比科技股份有限公司
Junghe, Taipei, Taiwan
Phone +886 2 8227 3966
www.cab.de/tw
info.asia@cab.de

China 中国

cab (Shanghai) Trading Co., Ltd.
铠博(上海)贸易有限公司
Phone +86 21 6236-3161
www.cab.de/cn
info.cn@cab.de

Representatives in other countries on request.

1	Introduction	3
2	Check firmware version of printer	4
3	Printer configuration.....	6

1 Introduction

Important information and instructions in this documentation are designated as follows:



Warning!

Indicates a hazardous situation that could lead to injuries or material damage.



Attention!

Draws attention to possible dangers, material damage or loss of quality.



Notice!

Gives you tips. They make a working sequence easier or draw attention to important working processes.

- ▶ Handling instruction.
- ▷ Reference to section, position, illustration number or document.
- * Option (accessories, devices, special fittings).

Hour Information in the display.

Step 1 : check firmware version of printer in **Short status** menu.



Figure 1 Short status




Figure 2 Firmware version

Step 2 : compare with the last version available on cab website:




Figure 3 Firmware on cab website



Information !

In order to operate properly all features of your printer and cablabel S3, it is recommended to use the latest available firmware and software versions:

Firmware : ▷ <https://www.cab.de/fr/support/support-telechargements/?suchtyp=art&gruppierung=9&kategorie=48>

cablabel S3 : ▷ <https://www.cab.de/fr/support/support-telechargements/?suchtyp=art&gruppierung=9&kategorie=63>

2 Check firmware version of printer

5

Step 3 : when needed, download and unpack the ZIP archive into a folder.



Figure 4 Unpacked folder

Step 4 : then update the firmware, with for example the "cabFirmwareUpdater" tool:




Figure 5 cabFirmwareUpdater

Simply check the used code page in the printer.

This one must match with the one used by cablabel S3 software (UTF-8).

To check the used code page in the printer:

- ▶ Press the `menu` key
- ▶ Go into `Setup => Interfaces => Character set` menu
- ▶ Check if this parameter is set on `UTF-8`




Figure 6 Setup




Figure 7 Interfaces




Figure 8 Code page



Warning !

This setting is needed for printing texts with special characters, like for example accented characters, Arabic, Chinese, Greek, Cyrillic ...